
## A Case Study in Implementing Standardized Restoration Monitoring in Mobile Bay Subwatersheds

Renee Collini

**National Monitoring Conference** 

May 4<sup>th</sup>, 2016






#### Introduc

**❖**"promote

Compreh

❖Non-regul

Many stak



### al Estuary

he system"

MP)

Committees

#### Science Advisory Committee

Experts


20 voting members; 30-40 participants

Estuary Status and Trends

Monitoring subcommittee



### Watershed Management Planning



## Why a Monitoring Framework?

Lots of restoration & planning

Different people doing different things

Different focus areas/issues



## Why a Monitoring Framework?

What are the baselines?

Are the efforts affecting change?

Needed standardize and scalable monitoring



# What is in the Framework? Recommendations

Sampling

**Parameters** 

Timing & Frequency

Location

Methodology

Efficiency


Data storage & usage


Implementation

MOBILE BAY NATIONAL ESTUARY PROGRAM

#### Mobile Bay Subwatershed Restoration Monitoring Framework

Science Advisory Committee: Monitoring Working Group, 2015





#### Deterrents to Monitoring

Expense

Expertise



Time

People



Spread the job around = better chances??

#### D'Olive Sampling

Parameters cover:

Water quality

Sedimentation & flow

Habitat quality & quantity

12 Agencies & 27 individuals working on data collection

480 water quality samples taken daily



60 parameters sampled in 76 days annually

#### Positives

Lot of data, little money

Burden sharing

Strengthen inter-agency relationships

Mechanisms to continue



Community buy-in

#### Challenges

#### Coordination

- Between monitoring groups
- Between monitoring & restoration efforts

Timing Redundancy

Funding/Resources

Reporting




Data Management: Storage & Metadata

#### Moving Forward

Other Watersheds

Adjust for lessons learned
Restoration schedule
Reporting schedule
Metadata template
Public data repository



Maintain long-term monitoring

Summary

Already existing networks

Big undertaking

Requires great people

Cost effective

Specific considerations

S



Quantify changes

#### Acknowledgements































#### Parameters: Water Quality Sondes

Samples are taken at 15 min intervals at 5 stations throughout the watershed: 1 at the end of a large restoration, the other 4 at downstream cumulative sites.

Depth

Temperature

Dissolved Oxygen

Conductivity

**Turbidity** 

рН

#### Parameters: Sedimentation & Flow

Samples are taken 3 times annually: Once during baseflow and twice during rain events. These samples will be plugged into a sediment transport model that has already been developed for the watershed. Samples taken at strategic downstream sites and cumulative sites.

Samples Taken

Total Bed Sediment

Total Suspended Sediment

Bed Sediment Transport (using a BSRD)

Stream Discharge

**Nutrients** 

рΗ

Conductivity

Turbidity

Temperature

Dissolved Oxygen

Rates Calculated

Bed Sediment Transport Rates

Suspended Sediment Transport Rates

Total Sediment Transport Rates

Bed Sediment Loading

#### Parameters: Freshwater Wetlands

Acreage
Wetland Rapid Assessment Protocol
(WRAP)
Wildlife Utilization
Wetland Overstory/Shrub Canopy
Wetland Vegetative Ground Cover
Adjacent Upland Support/Wetland Buffer
Field Indicators of Wetland Hydrology

Water Quality Input and Treatment Systems

Floristic Quality Index (FQI)

List of all species

*List of all native species* 

Total # of species

Total # of native species

Percent tolerant species

Percent intolerant species

Percent wetness

#### Parameters: Streams & Riparian Buffers

#### Stream Health Index

Percent Ground Cover of Organic Matter

Buffer Width

Presence of Non-natives

Bank Erosion Hazard Index (BEHI)

Basal Area

Structural Diversity of the Canopy

Bank Root Density

#### Parameters: Intertidal Marshes & Flats

Acreage

Hydrogeomorphic Approach (HGM)

Wetland Patch Size

Adjacent Land Use

Mean Marsh Width

Wave Energy Exposure

Aquative Edge

Hydrologic Regime

Nekton Habitat Diversity

Wildlife Habitat Diversity

Mean Percent Cover Emergent Marsh Vegetation

Vegtation Height

Percent Cover of Invasive or Exotic Species

Percent Cover by Woody Plant Species

Weltand Indicator Status

#### Parameters: D'Olive Bay

Samples conducted monthly from April - November, and every other month the rest of the year at three locations throughout the bay: High, Mid, and Low.

Photosynthetically Active Radiation

Salinity

Temperature

Dissolved Oxygen

Chl-a

Turbidity

Total Suspended Solids

Colored Dissolved Organic Matter